


1.-Ingresa a radio.inimusic.com, introduce tu usuario y contraseña proporcionados por mashter.com



Te aparecera la sig. ventana



3.- Ingresa a **Quick Links** , ahí es donde te aparecera informacion nesesaria para transmitir radio

The screenshot displays the radio.inimusic.com client interface. The main content area is divided into several sections:

- Quick Links:** Provides the stream start page (<http://radio.inimusic.com/start/demolandiaradio>) and the streaming server index page (<http://173.192.42.39:6002/index.html>).
- Tune-In Links:** Lists links for Winamp, iTunes, Windows Media Player, Real Player, and QuickTime, all pointing to the streaming server.
- Live Source Connections:** Provides instructions for configuring live source software. It specifies:
  - Server hostname: **173.192.42.39**
  - Maximum bit rate: **64**
  - Server type: **SHOUTcast v2**
  - Server port: **6002**
  - Password: (The 'Source password' value from your stream settings)
- FTP Client Connections:** Provides instructions for configuring FTP client software to upload media for the autoDJ:
  - FTP Hostname: **173.192.42.39**
  - FTP Username: **demolandiaradio**
  - FTP Password: (Your administrator password)

On the left side, there is a sidebar with navigation options: Configuration (Settings, Widgets, DJs), Statistics (Report, Listeners, Logs), Server (Stop, Restart, Admin), and Session (Log Out). A red 'X' icon is visible next to the Session option.

Below the sidebar, a white box contains the text: "ESTOS SON LOS DATOS IMPORTANTES PARA TRANSMITIR". Arrows point from this text to the configuration details in the Live Source Connections section, specifically to the fields for "DIRECCION O HOSTNAME", "PUERTO DE TRANSMISION", and "SOURCE PASSWORD".

On the right side, there is a section titled "Ejemplo configuracion de Winamp" with instructions: "En winamp poner en ID DE USUARIO tu HOST, en PORT tu SERVER PORT , en CONTRASEÑA tu SOURCE PASSWORD". Below this is a screenshot of the "Nullsoft SHOUTcast Source" window, showing the "Salida" (Output) tab with "Salida 1" selected and "Estado" (Status) set to "No Conectado". The "Conexión" (Connection) tab shows the "Configuración de salida" (Output configuration) with "Dirección" (Address) set to "173.192.42.39", "Puerto" (Port) set to "6002", and "Stream ID" set to "1". The "ID de usuario" (Username) is "demolandiaradio" and the "Contraseña" (Password) is masked with dots.

**CON ESTA CONFIGURACION YA PODRAS TRANSMITIR TU RADIO POR INTERNET**

4.- Para crear Locutores (DJ'S) para que cada uno tenga su propia sesión para transmitir, dar click en **DJ'S** , despues en **Create DJ account** para crea el locutor y de click en **SAVE**.

**Configuration**  
Settings | Widgets | DJs

**Statistics**  
Report | Listeners | Logs

**Server**  
Stop | Restart | Admin

**Session**  
Log Out

### DJ Account Settings

Username:

Password:

Confirm password:

Real name:

Status:

### Privileges

Permissions:   
(Hold Ctrl to select multiple.)

- Start/stop the stream
- Start/stop the autoDJ
- Manage playlist settings
- Access media library
- Manage media files
- View statistics
- View listeners
- View logs

### Login Restrictions

Allow logins:   
(Hold Ctrl to select multiple.)

Allow from:  :  :

Allow until:  :  :

Save

5.- ahora en winamp la configuracion solo cambia el ID DE USUARIO Y LA CONTRASEÑA QUE SERAN LOS DATOS DEL LOCUTOR EN TURNO



**NOTA IMPORTANTE: RECUERDA QUE ESTA CONFIGURACION SOLO TE DICE QUE HOSTNAME, PUERTO, USUARIO, CONTRASEÑA VAS A USAR, TU CONFIGURACION COMPLETA DEPENDE DEL REPRODUCTOR QUE UTILICES PARA TRANSMITIR (virtual dj, winamp, sam, etc)**

